

ESP32 DataLogger CLI - Complete User Manual

Table of Contents

- 1. [Installation](#)
- 2. [Connection Options](#)
- 3. [Data Retrieval Commands](#)
- 4. [RTC \(Real-Time Clock\) Commands](#)
- 5. [Sensor Reading Commands](#)
- 6. [Configuration Commands](#)
- 7. [LED Heartbeat Commands](#)
- 8. [Storage Management Commands](#)
- 9. [System Control Commands](#)
- 10. [Error Messages](#)
- 11. [Troubleshooting](#)

Installation

Requirements

- Python 3.6 or higher
- PySerial library

Install Dependencies



bash

```
pip install pyserial
```

Download Script

Save datalogger_cli.py to your computer and make it executable (Linux/Mac):



bash

```
chmod +x datalogger_cli.py
```

Connection Options

These options control how the tool connects to your datalogger device.

--port <PORT>

Description: Specify the serial port to connect to.

Usage:



bash

```
# Windows
python datalogger_cli.py --port COM19 --list

# Linux
python datalogger_cli.py --port /dev/ttyUSB0 --list

# Mac
python datalogger_cli.py --port /dev/cu.usbserial-XXX --list
```

When to use:

- When auto-discovery fails
- When you have multiple devices
- For scripts requiring explicit port control

Default: Auto-discovery enabled (no port needed)

--baud <RATE>

Description: Set the serial communication baud rate.

Usage:



bash

```
python datalogger_cli.py --port COM19 --baud 115200 --list
```

Default: 115200 (matches firmware default)

Note: Only change if your firmware uses a different baud rate.

--discover / --no-discover

Description: Enable or disable automatic device discovery.

Usage:



bash

```
# Enable auto-discovery (default)
python datalogger_cli.py --discover --list

# Disable auto-discovery (requires --port)
python datalogger_cli.py --no-discover --port COM19 --list
```

When to use --no-discover:

- Multiple serial devices connected
- Faster connection when port is known
- Scripted/automated operations

--reset

Description: Toggle DTR/RTS lines to reset the device before connecting.

Usage:



bash

```
python datalogger_cli.py --reset --port COM19 --list
```

When to use:

- Device is unresponsive
- After uploading new firmware
- To force a fresh start

--no-progress

Description: Disable progress bar during file downloads.

Usage:



bash

```
python datalogger_cli.py --date 2025-10-07 --no-progress
```

When to use:

- Logging output to files
- Running in scripts/cron jobs
- Cleaner console output

Data Retrieval Commands

--list

Description: List all available date logs with file sizes and row counts.

Usage:



bash

```
python datalogger_cli.py --list
```

Example Output:



Available logs (5 dates):

2025-10-01	127 KB	412 rows
2025-10-02	145 KB	485 rows
2025-10-03	138 KB	461 rows
2025-10-04	152 KB	506 rows
2025-10-07	83 KB	276 rows

Information Shown:

- **Date:** YYYY-MM-DD format
- **Size:** File size in kilobytes
- **Rows:** Number of data records (excluding header)

When to use:

- Before downloading to see what's available
- Check storage usage
- Verify logging is working

--date <YYYY-MM-DD>

Description: Download CSV file for a specific date.

Usage:



bash

```
# Download to default location (./logs/2025-10-07.csv)
python datalogger_cli.py --date 2025-10-07

# Download to specific location
python datalogger_cli.py --date 2025-10-07 --out D:\Data\today.csv

# Download multiple dates
python datalogger_cli.py --date 2025-10-05 --out ./day1.csv
python datalogger_cli.py --date 2025-10-06 --out ./day2.csv
python datalogger_cli.py --date 2025-10-07 --out ./day3.csv
```

Example Output:



```
Downloading 2025-10-07...
Downloading... 100% (84523/84523 bytes)
✓ Saved: ./logs/2025-10-07.csv (84,523 bytes)
```

CSV Format:



```
csv

time,temperature,humidity,vbat_mV
08:00:00,25.34,62.15,3712
08:05:00,25.41,61.98,3710
08:10:00,25.38,62.07,3709
```

Features:

- CRC32 verification (automatic)

- Resume capability (uses .part temp file)
 - Progress indicator (disable with --no-progress)
-

--out <PATH>

Description: Specify output file path for downloaded CSV.

Usage:



bash

```
python datalogger_cli.py --date 2025-10-07 --out ./data/measurement.csv
```

Default: ./logs/<date>.csv

Tips:

- Directories are created automatically
 - Use absolute or relative paths
 - Extension should be .csv
-

RTC (Real-Time Clock) Commands

--time

Description: Query the current date and time from the RTC.

Usage:



bash

```
python datalogger_cli.py --time
```

Example Output:



```
Current time: 2025-10-07 14:35:22
```

When to use:

- Verify RTC is set correctly

- Check if battery backup is working
- After power loss

Format: YYYY-MM-DD HH:MM:SS (24-hour format)

--settime [TIMESTAMP]

Description: Set the RTC to a specific time or sync with PC time.

Usage:



bash

Set to current PC time (easiest)

```
python datalogger_cli.py --settime now
```

Set to specific time

```
python datalogger_cli.py --settime "2025-10-07 14:30:00"
```

Without argument defaults to 'now'

```
python datalogger_cli.py --settime
```

Example Output:



```
✓ RTC set to: 2025-10-07 14:30:00
```

Important Notes:

- RTC will keep running even after power loss (if battery present)
- Use quotes for specific timestamps
- Format must be: YYYY-MM-DD HH:MM:SS
- Time is set in 24-hour format

Common Scenarios:



bash

Initial setup

```
python datalogger_cli.py --settime now
```

After battery replacement

```
python datalogger_cli.py --settime now
```

Set to specific moment (e.g., experiment start)

```
python datalogger_cli.py --settime "2025-10-07 09:00:00"
```

Sensor Reading Commands

--sense

Description: Read current temperature, humidity, and battery voltage.

Usage:



bash

```
python datalogger_cli.py --sense
```

Example Output:



Temperature: 25.34°C

Humidity: 62.15%

Battery: 3712 mV (3.712 V)

Sensor Details:

- **Temperature:** SHT4x sensor, ±0.2°C accuracy
- **Humidity:** SHT4x sensor, ±2% RH accuracy
- **Battery:** Voltage divider measurement

When to use:

- Quick health check
- Verify sensors are working
- Monitor battery level
- Check environmental conditions

Note: Battery voltage shown only if firmware supports it.

--vbat

Description: Query battery voltage only (faster than --sense).

Usage:



bash

```
python datalogger_cli.py --vbat
```

Example Output:



```
Battery: 3712 mV (3.712 V)
```

Voltage Ranges:

- **4.2V:** Fully charged (LiPo/Li-ion)
- **3.7V:** Nominal voltage
- **3.3V:** Low battery warning
- **3.0V:** Critical (device may shutdown)

When to use:

- Regular battery monitoring
- Before field deployment
- Troubleshooting power issues

Configuration Commands

--interval

Description: Query the current data logging interval.

Usage:



bash

```
python datalogger_cli.py --interval
```

Example Output:



Logging interval: 300 seconds (5.0 minutes)

When to use:

- Verify configuration after setup
- Check settings before data collection
- Document experiment parameters

--setinterval <SECONDS>

Description: Set the data logging interval (time between measurements).

Usage:



bash

Set to 1 minute

```
python datalogger_cli.py --setinterval 60
```

Set to 5 minutes

```
python datalogger_cli.py --setinterval 300
```

Set to 15 minutes

```
python datalogger_cli.py --setinterval 900
```

Set to 1 hour

```
python datalogger_cli.py --setinterval 3600
```

Example Output:



✓ Interval set to: 300 seconds (5.0 minutes)

Constraints:

- **Minimum:** 30 seconds
- **Maximum:** 86400 seconds (24 hours)
- Values outside range are clamped by firmware

Common Intervals:

Interval Seconds		Use Case
30 sec	30	High-resolution monitoring
1 min	60	Rapid changes
5 min	300	Standard logging
15 min	900	Long-term monitoring
30 min	1800	Slow processes
1 hour	3600	Daily patterns

Storage Calculation:

- Each row $\approx$ 50 bytes
- 1 day @ 5 min = 288 rows $\approx$ 14 KB/day
- 1 month @ 5 min $\approx$ 420 KB

When to use:

- Initial device setup
- Changing experiment requirements
- Balancing resolution vs. storage

LED Heartbeat Commands

The heartbeat LED provides visual feedback that the logger is alive and logging.

--heartbeat

Description: Query current heartbeat LED status and blink period.

Usage:



bash

```
python datalogger_cli.py --heartbeat
```

Example Output:



Heartbeat LED: ENABLED
Heartbeat period: 10 seconds

When to use:

- Check if LED is enabled
- Verify blink period setting
- Troubleshooting LED issues

--heartbeat-on

Description: Enable the heartbeat LED.

Usage:



bash

```
python datalogger_cli.py --heartbeat-on
```

Example Output:



✓ Heartbeat LED enabled

When to use:

- Field deployment (visual confirmation)
- Demonstrations
- Troubleshooting (verify device is alive)

Behavior:

- LED blinks periodically
- Period set by --setheartbeat
- Continues even during deep sleep

--heartbeat-off

Description: Disable the heartbeat LED.

Usage:



bash

```
python datalogger_cli.py --heartbeat-off
```

Example Output:



```
✓ Heartbeat LED disabled
```

When to use:

- Battery conservation (saves ~1-2 mA average)
- Light-sensitive experiments
- Stealth monitoring

--setheartbeat <SECONDS>

Description: Set the heartbeat LED blink period.

Usage:



bash

```
# Blink every 5 seconds
python datalogger_cli.py --setheartbeat 5
```

```
# Blink every 10 seconds
python datalogger_cli.py --setheartbeat 10
```

```
# Blink every 30 seconds
python datalogger_cli.py --setheartbeat 30
```

```
# Blink every minute
python datalogger_cli.py --setheartbeat 60
```

Example Output:



✓ Heartbeat period set to: 10 seconds

Recommended Periods:

- **5 seconds:** High visibility (uses more power)
- **10 seconds:** Balanced (default)
- **30 seconds:** Low power
- **60 seconds:** Ultra low power

Power Impact:

- Shorter period = more blinks = more power
- Each blink $\approx$ 20mA for $\sim$ 100ms

Storage Management Commands

--flash-info

Description: Display complete flash partition table.

Usage:



bash

python datalogger_cli.py --flash-info

Example Output:



Internal Flash (all partitions)				
Type/Sub	Label	Address	Size	Encrypted
APP /factory	factory	0x010000	1.00 MB	no
DATA /nvs	nvs	0x009000	24.00 KB	no
DATA /phy	phy_init	0x00F000	4.00 KB	no
DATA /littlefs	spiffs	0x110000	2.88 MB	no

Information Shown:

- **Type:** APP (program) or DATA (storage)
- **Subtype:** Partition purpose (factory, nvs, littlefs, etc.)
- **Label:** Partition name
- **Address:** Flash memory location
- **Size:** Partition capacity
- **Encrypted:** Whether flash encryption is enabled

When to use:

- Understanding device storage layout
- Verifying partition sizes
- Troubleshooting storage issues
- Technical documentation

--flash-free

Description: Quick summary of LittleFS storage usage.

Usage:



bash

```
python datalogger_cli.py --flash-free
```

Example Output:



```
=====
LittleFS (quick usage)
=====

Mount   : OK
Total   : 2949120 (2.81 MB)
Used    : 421888 (412.00 KB)
Free    : 2527232 (2.41 MB)
Free %  : 85.69%
```

When to use:

- Quick storage check
- Before logging long experiments
- Deciding when to download/delete data

Storage Guidelines:

- **>50% free:** Plenty of space
- **20-50% free:** Consider downloading data
- **<20% free:** Download and delete old logs
- **<10% free:** Critical, may stop logging

--flash-verbose

Description: Detailed LittleFS partition and usage information.

Usage:



bash

```
python datalogger_cli.py --flash-verbose
```

Example Output:



Partition (LittleFS on internal flash)

Label : spiffs
Type/Sub : DATA / littlefs
Address : 0x110000
Size : 2949120 (2.81 MB)
Encrypted : no

LittleFS (usage)

Mount : OK
Total : 2949120 (2.81 MB)
Used : 421888 (412.00 KB)
Free : 2527232 (2.41 MB)
Free % : 85.69%

When to use:

- Comprehensive storage analysis
- Technical troubleshooting
- Documentation and reporting

--delete <YYYY-MM-DD>

Description: Delete a specific date's log folder and all its files.

Usage:



bash

```
# Delete single date
python datalogger_cli.py --delete 2025-10-01

# Delete multiple dates (run separately)
python datalogger_cli.py --delete 2025-10-01
python datalogger_cli.py --delete 2025-10-02
python datalogger_cli.py --delete 2025-10-03
```

Example Output:



✓ Deleted 2025-10-01

Files removed: 3

Space freed: 127 KB (130,048 bytes)

What Gets Deleted:

- /logs/YYYY-MM-DD/ folder
- CSV file inside
- Any other files in that date folder

Safety:

- Requires exact date match
- Non-reversible operation
- Download data before deleting

When to use:

- Free up storage space
- Remove old/unwanted data
- After backing up to PC

Best Practice:



bash

1. List available logs

```
python datalogger_cli.py --list
```

2. Download what you want to keep

```
python datalogger_cli.py --date 2025-10-01 --out ./backup/2025-10-01.csv
```

3. Verify download

```
ls -lh ./backup/2025-10-01.csv
```

4. Delete from device

```
python datalogger_cli.py --delete 2025-10-01
```

--format <CODE>

Description: Format (erase) entire LittleFS storage. **DESTRUCTIVE!**

Usage:



bash

```
# Default code is 246810 (check your firmware)
python datalogger_cli.py --format 246810
```

Example Output:



```
Formatting storage...
✓ Storage formatted
Total: 2,949,120 bytes
Used: 0 bytes
Free: 2,949,120 bytes
```

⚠ WARNING:

- ALL DATA WILL BE LOST
- Cannot be undone
- Requires security code
- Use only when necessary

Security:

- Default code: 246810 (set in firmware)
- Change code with --setfmtcode
- Max 3 attempts per session
- Code stored in NVS (survives format)

When to use:

- Device malfunction/corruption
- Factory reset
- Selling/transferring device
- File system errors

Before Formatting:

1. Download all important data
 2. Verify downloads are complete
 3. Have security code ready
 4. Understand data will be lost
-

--setfmtcode <OLD> <NEW>

Description: Change the format security code.

Usage:



bash

```
# Change from default (246810) to custom code
python datalogger_cli.py --setfmtcode 246810 mynewcode123

# Change code again
python datalogger_cli.py --setfmtcode mynewcode123 anothernewcode
```

Example Output:



✓ Format security code changed

Requirements:

- Must provide correct old code
- New code: 4-32 characters
- Cannot reuse old code
- Authentication required

Security Best Practices:

- Use unique code per device
- Store code securely
- Don't share with unauthorized users
- Document code in safe location

When to use:

- Initial device setup
- Security policy compliance
- After unauthorized access attempt
- Transferring device ownership

System Control Commands

--reboot

Description: Restart the datalogger device.

Usage:



bash

```
python datalogger_cli.py --reboot
```

Example Output:



```
✓ Device rebooting... (reason: user)
```

What Happens:

- 1. Saves current state
- 2. Closes file system safely
- 3. Performs soft reset
- 4. Device starts fresh
- 5. Resumes logging automatically

When to use:

- After changing configuration
- Device seems unresponsive
- After firmware update
- Clear temporary errors

Safe to Reboot:

- Data is saved before reboot
- RTC keeps time (battery backup)
- Settings preserved in NVS
- Logging resumes automatically

Error Messages

Connection Errors

ERROR: Failed to open COM19: [Errno 2] could not open port

Cause: Port doesn't exist or is in use. **Solution:**

- Check Device Manager (Windows) or `ls /dev/tty*` (Linux)
- Close other programs using the port
- Try unplugging and replugging USB

ERROR: Could not auto-discover device. Use `--port.`

Cause: No device found on any port. **Solution:**

- Manually specify port: `--port COM19`
- Check USB connection
- Verify device is powered on
- Try `--reset` flag

Warning: No 'OK' to HELLO; continuing anyway.

Cause: Device didn't respond to handshake. **Solution:**

- Usually safe to ignore
 - Try `--reset` if commands fail
 - Check baud rate (should be 115200)
-

Command Errors

ERR code=RTC msg="not found"

Cause: RTC hardware not detected. **Solution:**

- Check I2C wiring (SDA, SCL)
- Verify RTC is powered
- Check firmware I2C configuration

ERR code=SHT4X msg="not found"

Cause: Temperature sensor not detected. **Solution:**

- Check sensor wiring
- Verify sensor power
- Test with `--sense` repeatedly

ERR code=BAD_DATE msg="format YYYY-MM-DD"

Cause: Invalid date format. **Solution:**

- Use exact format: `2025-10-07`
- Check year (2000-2099)
- No extra spaces

ERR code=NOT_FOUND msg="no file for 2025-10-07"

Cause: No log exists for that date. **Solution:**

- Use `--list` to see available dates
- Check spelling
- Verify device was logging on that date

ERR code=AUTH msg="bad_code"

Cause: Incorrect format security code. **Solution:**

- Check default code (usually 246810)
- Verify code hasn't been changed
- Contact administrator if lost

ERR code=LOCKED msg="too many attempts"

Cause: Multiple failed format attempts. **Solution:**

- Reboot device: --reboot
- Try again with correct code
- Wait for session timeout

ERR code=NVS msg="write failed"

Cause: Non-volatile storage write error. **Solution:**

- Try command again
- Reboot device
- Check for corruption (rare)

Download Errors

CRC mismatch: got 12345678, expected 87654321

Cause: Data corruption during transfer. **Solution:**

- Try download again
- Check USB cable quality
- Use shorter/better cable
- Reduce interference

Timeout waiting for DATA

Cause: Device didn't send file data. **Solution:**

- File might not exist (check --list)
- Try again
- Reboot device if persistent

Troubleshooting

Device Not Responding

Symptoms:

- Commands timeout
- No response to HELLO
- Connection established but no data

Solutions:

1. Try hard reset:



bash

```
python datalogger_cli.py --reset --port COM19 --time
```

2. Manually reboot device:



bash

```
python datalogger_cli.py --reboot
```

3. Check power:



bash

```
python datalogger_cli.py --vbat
```

If battery < 3.0V, charge/replace

4. Verify port and baud:



bash

```
python datalogger_cli.py --port COM19 --baud 115200 --list
```

Slow Downloads

Symptoms:

- Download takes several minutes
- Progress bar moves slowly

Causes:

- Large files (normal)
- USB interference
- Poor cable

Solutions:

1. Use --no-progress for cleaner output:



bash

```
python datalogger_cli.py --date 2025-10-07 --no-progress
```

2. Use shorter/better USB cable
3. Reduce USB hub hops (direct connection)
4. Check file size first:



bash

```
python datalogger_cli.py --list
```

Storage Full

Symptoms:

- Free % near 0%
- Cannot download newer logs
- Device stops logging

Solutions:

1. Download all data:



bash

```
python datalogger_cli.py --list  
# Download each date
```

2. Delete old logs:



bash

```
python datalogger_cli.py --delete 2025-09-01
```

```
python datalogger_cli.py --delete 2025-09-02
```

3. Check free space:



```
bash
```

```
python datalogger_cli.py --flash-free
```

4. Last resort - format (loses all data):



```
bash
```

```
python datalogger_cli.py --format 246810
```

RTC Losing Time

Symptoms:

- Time resets after power loss
- Time drift over days
- Wrong timestamps in logs

Solutions:

1. Set time:



```
bash
```

```
python datalogger_cli.py --settime now
```

2. Check RTC battery (if removable)

3. Verify RTC responds:



```
bash
```

```
python datalogger_cli.py --time
```

4. If persistent, may be hardware issue

Permission Denied (Linux/Mac)

Symptoms:



```
ERROR: [Errno 13] Permission denied: '/dev/ttyUSB0'
```

Solutions:

1. Add user to dialout group:



```
bash
```

```
sudo usermod -a -G dialout $USER
```

Log out and back in

2. Temporary fix (not recommended):



```
bash
```

```
sudo python3 datalogger_cli.py --port /dev/ttyUSB0 --list
```

3. Check port ownership:



```
bash
```

```
ls -l /dev/ttyUSB0
```

Quick Reference Card

Essential Commands



bash

Connection

--port COM19 # Specify port
--discover # Auto-find device (default)
--reset # Reset before connecting

Data

--list # Show available logs
--date 2025-10-07 # Download specific date
--out ./file.csv # Custom output path

RTC

--time # Show current time
--settime now # Set to PC time

Sensors

--sense # Temp, humidity, battery
--vbat # Battery voltage only

Config

--interval # Show log interval
--setinterval 300 # Set to 5 minutes

LED

--heartbeat # Show LED status
--heartbeat-on # Enable LED
--setheartbeat 10 # Set 10 sec period

Storage

--flash-free # Show storage space
--delete 2025-10-01 # Delete date logs
--format 246810 # Format storage (DANGER!)

System

--reboot # Restart device

Common Workflows

Initial Setup:



bash

```
python datalogger_cli.py --settime now
python datalogger_cli.py --setinterval 300
python datalogger_cli.py --heartbeat-on
python datalogger_cli.py --sense
```

Daily Check:



bash

```
python datalogger_cli.py --time
python datalogger_cli.py --vbat
python datalogger_cli.py --flash-free
python datalogger_cli.py --list
```

Data Retrieval:



bash

```
python datalogger_cli.py --list
python datalogger_cli.py --date 2025-10-07 --out ./data.csv
```

Maintenance:



bash

```
python datalogger_cli.py --list
python datalogger_cli.py --delete 2025-09-01
python datalogger_cli.py --flash-free
```

Support & Documentation

For additional help:

- Run `python datalogger_cli.py -h` for command list
- Check firmware documentation for hardware details
- Verify firmware version supports all commands

- Contact technical support for hardware issues
-

Document Version: 1.0

Last Updated: October 2025

Compatible Firmware: v1.x with all serial commands